

Module 2 – IPv6 OSPF Areas

Objective: To implement OSPF areas, neighbour authentication and area summarisation in the lab network.

Prerequisite: Module 1 and OSPF presentation

Topology:




Figure 1 – OSPF Areas

Lab Notes

This module provides an introduction to areas in OSPF as used in ISP networks. The module forms the basis for the Route Reflector Module which follows. It is strongly recommended that the OSPF presentation is reviewed prior to starting this module. Prerequisites for this Module are Module 1, and the OSPF presentation. As before, ask the workshop instructors or refer to the CD Documentation if there is any doubt.

Before starting, decide which routers in the network will represent the core network, and which will represent other portions of the backbone. The example given in Figure 1 allows the student to configure the best combination for the study of OSPF areas.

Functional assignments of routers in Figure 1:

- Routers 5 to 10 represent the “core network” and the core interfaces are all in OSPF area 0. In a typical ISP backbone, these routers would carry all the internal link routes known in the ISPs network. Routers 5, 6, 9 and 10 are **Area Border Routers**, whereas Routers 7 and 8 are **Internal Routers**.
- Routers 1 and 3 are completely in OSPF area 10. Router 5 is the boundary between area 0 and area 10, so requires configuration for both areas.
- Routers 2 and 4 are completely in OSPF area 20. Router 6 is the boundary between area 0 and area 20, so requires configuration for both areas.
- Routers 11 and 13 are completely in OSPF area 30. Router 9 is the boundary between area 0 and area 30, so requires configuration for both areas.
- Routers 12 and 14 are completely in OSPF area 40. Router 10 is the boundary between area 0 and area 40, so requires configuration for both areas.

Note: if this module is attempted without completing the IPv4 version, please remember to set the OSPF router-id first.

Lab Exercise

1. **Reset the configuration of each router** so that it is as it was at the end of Step 14 of Module 1. Also, shutdown or disconnect interfaces which are not being used for this Module. These include connections between Router1 and Router2, Router1 and Router13, Router2 and Router14, and Router13 and Router14. It makes no sense to have a physical connection between non-zero OSPF areas as traffic between two non-zero areas must always transit Area 0.

Important: There should be no OSPFv3 or BGP running in the lab network. Also ensure that there are no access-lists or route-maps remaining on the routers. Unused configuration should be deleted. OSPF and BGP configuration can be deleted by entering the commands:

```
no router bgp <ASN>
no ipv6 router ospf <PID>
```

Checkpoint #1: *Call the lab assistant and show the router configuration and connectivity.*

2. **OSPF Configuration for routers in Area 0 only.** Configure OSPF for your router using PID 41. Remember all the tips and techniques which you have learned in previous module. Recall how to

use the *ip ospf 41 area N* command on each interface. Also recall the use of the *passive-interface default* command. You only want to configure OSPF with other routers in Area 0. Do **not** configure OSPF with routers in areas 10 to 40 yet.

Example for Router 5:

```
ipv6 router ospf 41
  passive-interface default
  no passive-interface serial 0/0
  no passive-interface ethernet 0/0
!
interface serial 0/0
  ipv6 ospf 41 area 0
interface ethernet 0/0
  ipv6 ospf 41 area 0
interface loopback 0
  ipv6 ospf 41 area 0
!
```

- 3. OSPF configuration for routers with interfaces in Areas 10 to 40 only.** Configure OSPF for your router using PID 41. Remember the tips and techniques which you have learned in previous modules. Recall how to use the *ip ospf 41 area N* command on each interface. Also recall the use of the *passive-interface default* command. You only want to configure OSPF with other routers which have interfaces in your own area. Do **not** configure OSPF with routers in area 0 yet.

Example for Router 11:

```
ipv6 router ospf 41
  passive-interface default
  no passive-interface serial 0/0
  no passive-interface serial 0/1
!
interface serial 0/0
  ipv6 ospf 41 area 30
interface serial 0/1
  ipv6 ospf 41 area 30
interface loopback 0
  ipv6 ospf 41 area 30
```

Checkpoint #2: Call the lab instructors and show the function of your router. You should have neighbour relationships with all the routers in your area (called intra-area). You should also demonstrate the output from “show ip route” so that you can see which routes you are hearing from which routers.

- 4. Putting it all together!** We have now configured OSPF in the routers which are wholly in a particular area. We now need to join the areas together to rebuild our OSPF network. The next step should be carried out by the appropriate router teams to achieve this.
- 5. Connecting Area 0 to the Areas 10, 20, 30 and 40.** The teams running Routers 5, 6, 9 and 10, the Area Border Routers in the core of our lab network, now need to set up configuration so that the four other physically connected areas have an OSPF relationship with Area 0.

For example, the team operating Router 5 needs to activate OSPF on the interface which connects to Router 3 in Area 10 so that the routers can try to establish a neighbour relationship. An example configuration might be:

```
ipv6 router ospf 41
  no passive-interface serial 0/1
!
interface serial 0/1
  ipv6 ospf 41 area 10
```

This tells the router that the OSPF neighbour it finds will be in OSPF area 10, which is a stub area.

Routers 6, 9, and 10 should enter similar and appropriate configuration for their non-area 0 neighbours.

- 6. All router teams should check their routing table.** The routing table should look the same as it did in Module 1. All the prefixes in Area 0 will be available in Areas 10 through to 40. Although notice now that several of the routes will be marked as Inter Area (IA) routes.

Traces through the network. Once you have analysed the routing table as it is now, and compared with any notes you made in Module 1, try some traceroutes through the network.

Checkpoint #3: *Call the lab instructors and show the function of your router. The inter-area OSPF “peerings” will now be up. If you have an area border router, demonstrate the neighbour relationships using “sh ip ospf neigh”. If you are not in an area border, you should now have a more complete routing table.*

STOP AND WAIT HERE

- 7. Intra Area Authentication.** OSPF supports router authentication within areas. This is quite important inside ISP networks to prevent the introduction of improperly configured or unintended equipment.

Each area will turn on authentication within that area. Routers which are **ABRs** will naturally have to enter configuration to cover all areas the router has interfaces in. This first step will enable each area to support authentication using the *area N authentication* command set.

We have to set a different Security Parameter Index (SPI) for each area. Please use the SPIs as listed below, otherwise each router team will have to negotiate SPIs for each area.

Area0	500	Area30	3000
Area10	1000	Area40	4000
Area20	2000		

An example configuration for Router6 might be:

```

ipv6 router ospf 41
 area 0 authentication ipsec spi 500 md5 0123456789ABCDEF0123456789ABCDEF
 area 20 authentication ipsec spi 2000 md5 0123456789ABCDEF0123456789ABCDEF
!
```

Notice now that the OSPF adjacencies do not come up unless the neighbouring router has also entered the same configuration and key. Notice also how the OSPF adjacencies timed out after the configuration was entered – the adjacent router still had not set up OSPF neighbour authentication. Once they also have done this, the adjacency is re-established.

Also, if we want to configure neighbour authentication per area but disable it on a per link basis, we need to use the authentication null option. The following example shows how to disable neighbour authentication on one specific interface, hssi 5/0.

```

interface hssi 5/0
 ipv6 ospf authentication null
 ipv6 ospf 1 area 10
```

Note: Wherever an OSPF session is configured from now on in the workshop, all Router Teams MUST use passwords on these OSPF sessions.

Checkpoint #4: Call the lab instructors and demonstrate the OSPF is still working following the addition of neighbour authentication and that the OSPF routing table is still the same as it was previously.

8. **Inter-area summarisation.** It is fairly important, especially for larger ISP networks, to try and summarise the announcements going from sub-areas into Area 0 as much as is possible. Unfortunately we don't have an extensive lab network here, so it's going to be hard to see much benefit from summarisation, but we will try with the limited resources we have.

Areas 10, 20, 30 and 40 can summarise the point-to-point links they announce into Area 0. Routers 5, 6, 9 and 10, respectively, will introduce this configuration into the network. We will take the example of Area 20 and Router 6 below. Area 20 point to point subnets are 2001:db8:0:6::/64 (Router2-Router4) and 2001:db8:0:7::/64 (Router4-Router6). These can be aggregated into 2001:db8:0:6::/63. The configuration which has to be introduced on Router6 therefore is:

```

ipv6 router ospf 41
 area 20 range 2001:db8:0:6::/63
```

Once the team operating Router6 has done this, check the routing table. Everyone (apart from Area 20 routers) will see that the entries for 2001:db8:0:6::/64 and 2001:db8:0:7::/64 will have been replaced by the aggregate, 2001:db8:0:6::/63.

9. The other three router teams (5, 9 and 10) should do a similar thing for their areas, aggregating the point to point links between their area routers. Once complete, eight /64s in the routing table should have been replaced by four /63 aggregates

10. Final check. Use the various “*show ipv6 ospf*” commands to see the OSPF status of the lab network now. Check the routing of IPv6 traffic and the IPv6 routing table. If you are missing any adjacencies, work with your neighbouring routers to work out why, and what might have gone wrong with the neighbour authentication.

Checkpoint #5: *Call the lab instructors and show the routing table after the area summarisation was applied.*

CONFIGURATION NOTES

Documentation is critical! You should record the configuration at each ***Checkpoint***, as well as the configuration at the end of the module.